


What it does: SteelyFusionFlow marks the opening range, scores each close beyond it from 0 to 10 across twelve layers of session context, and labels pattern setups around it. Signals are worked out once per **finished bar**, so live, F5 and Playback show the same signals.



MNQ, 5-minute: opening-range, IB and overnight lines, SWEEP BEAR, REJ BEAR and B&R MID BULL setups, and the HUD (top left). Shown for illustration only.

NEW TO THE OPENING RANGE

Read the chart at a glance

The opening range is the high and low of the first minutes of regular trading (09:30–09:45 ET by default). SteelyFusionFlow scores closes beyond it.

OR H / L / M	Opening-range high, low and midpoint. Nothing is scored until the range seals.
BULLISH n/10	The score reached the fire threshold. First per direction each session: PRIME ; later MINOR ones show only n/10.
B&R / REJ / MID TEST	Price tests the OR High, Low or Mid and a later close holds beyond it. B&R follows a PRIME .
FAIL BRK / SWEEP	A poke (FAIL BRK) or 2+ closes (SWEEP) beyond the range, then a close back inside. OR FADE : an edge test before any PRIME .
Projection 1–3	Drawn at the day's first signal: 61.8%, 100% and 161.8% of the range height beyond that edge; Pullback 61.8% back inside.
Key levels	PDH/PDL, TC/PP/BC (central pivot range), IBH/IBL (initial balance), ON H/L (overnight). Nearby levels add points.

Reading the HUD

Range	WAITING FOR ORB, BUILDING RANGE or RANGE COMPLETE, with OR High, Low, Mid and height.
Location	BULLISH BREAK, BEARISH BREAK or INSIDE RANGE: location only, not a signal.
Signal	Latest signal, e.g. BULLISH 10/10 @ 11:45 (the bullish one once both sides have fired).
Bull / Bear	Scores 0–10 as bars. Conf = 10 × the highest score, not a probability.

Hover any HUD row for a full explanation. Drag the panel anywhere; Show Verbose HUD adds the context rows.

FOR EXPERIENCED TRADERS

The rules, exactly

Range	Bars closing after ORB Start and by ORB End (09:30–09:45 ET) form the range. Times are ET in any time zone.
Score	2 points for a close beyond the sealed range, plus internal Alpha (up to 5), bias, EMA trend, RSI, ADX, flow, key levels, IB extension, CPR day type (±1); minus weak ADX, opposing flow, VWAP stretch.
Signals	Fire threshold: Conservative 10, Standard 8, Permissive 6, Aggressive 5. Later signals wait Cooldown Bars or a close back inside; Max Minor Signals caps only those scoring exactly the threshold.
Gates	LOW-VOL (ATR(20) under Min ATR Points) zeroes scores; COMPRESSION halves them. A first signal is blocked by a fully opposed EMA ribbon or a bar opening past the edge.
Cut-off	No scored signals after ORB Valid Until (16:15 ET). A break bar 1.5 × ATR(20) tall can lift a score within 1 point of the threshold (STRONG-BK).

Get started in three steps

- Find your license key and the download at whop.com/steelysystems (SteelyIndicators Download). Both are also in your purchase email.
- In NinjaTrader 8: Tools > Import > NinjaScript Add-On, then select SteelyIndicators.zip (keep it zipped).
- Right-click a chart > Indicators > add **SteelyFusionFlow**, and paste your license key when asked. Defaults are ready to use.

Useful settings

Signal Profile (Standard) · **ORB Start** / **ORB End** · **ORB Valid Until** · **Intrabar Signals** (off) · **Full Signal Labels** · **Show Verbose HUD** · **Enable Audio**. Right-click still opens the chart menu.