

What it does: SteelyORBFlow captures the opening range (09:30-09:45 ET by default), draws its High, Low and Mid, and marks each breakout: the first each way each day as **PRIME**, later ones as **RE-ARM**. Breakouts are decided at the **bar close** by default.



MNQ, 5-minute: range box, ORB High/Low/Mid lines, PRIME and RE-ARM up-break labels, projection levels and the HUD (top left). Shown for illustration only.

NEW TO OPENING RANGE BREAKOUTS

Read the chart at a glance

The first minutes after the New York open set a high and a low: the opening range. A close beyond either edge is a breakout. SteelyORBFlow draws the range and labels each breakout.

Range box	Shades the opening range while it builds; one per day.
ORB High / Low / Mid	The range's high, low and midpoint, fixed once the range is complete.
PRIME UP / DOWN BREAK	Green (up) or red (down): the first breakout that way today.
RE-ARM UP / DOWN BREAK	Cyan (up) or pink (down): a later breakout that way, after a close back inside.
Pullback · P1-P3	Dashed levels for the latest breakout's direction: Pullback 61.8% of the range back inside; P1-P3 at 61.8%, 100%, 161.8% beyond.

Reading the HUD

Status	WAITING FOR ORB, BUILDING RANGE or RANGE COMPLETE. An orange warning line under it: the bar size does not fit the window.
High / Low / Mid	Range levels and height; vs High and vs Low give the last price minus each edge.
Signal	Updates live: UP/DOWN BREAK (last arrow: PRIME or RE-ARM), ABOVE HIGH / BELOW LOW (no arrow), RECLAIM LOW, REJECT HIGH or INSIDE RANGE.
Filter	Would a RE-ARM pass its filters now: BOTH OK, UP OK, DOWN OK, BLOCKED or OFF.

Trend, Strength (0-10), Momentum, ADX, Bar Bias (candle volume, not bid/ask delta) and EMA Align add context. Hover any row for details.

FOR EXPERIENCED TRADERS

The rules, exactly

Range	Bars that close after the window start and at or before its end (5-minute, +0 to +15: 09:35, 09:40, 09:45 ET). Reset daily.
Breakout	A bar that opens at or inside the edge and closes beyond it. A gap open beyond the edge gets no arrow; one arrow per bar.
PRIME / RE-ARM	First arrow each way each day: PRIME, never filtered. A close back below ORB High (above ORB Low) re-arms; RE-ARM needs 3 more bars and its filters.
RE-ARM filters	Min ADX For RE-ARM: ADX(14) 20+ (0 = off). Optional: Use EMA Trend Filter (RE-ARM only), Require Bar Bias Alignment (65% / 35%).
Timing	Bar Close (default): arrow, projections and alerts at the close. Intrabar: arrow and alert once price qualifies; the arrow comes and goes with price until the close keeps or removes it.

Get started in three steps

1. Find your license key and the download at whop.com/steelysystems (SteelyIndicators Download). Both are also in your purchase email.
2. In NinjaTrader 8: Tools > Import > NinjaScript Add-On, then select SteelyIndicators.zip (keep it zipped).
3. Right-click a chart > Indicators > add **SteelyORBFlow**, and paste your license key when asked. Defaults are ready to use.

Useful settings

ORB Time Mode · ORB Capture Start / End (Min After Anchor) (0, 15) · Signal Timing · Min ADX For RE-ARM (20) · Show Range Projection Levels · Enable Screen Flash. Right-click still opens the chart menu.