

What it does: SteelyStoryTeller grades every closed bar on four parts (context, execution, flow and red flags), blends them into one 0–100 **Total Quality Score** (TQS), and explains the reading in plain words on the chart. A **PRIME** marker appears only when every gate passes.



MNQ, 5-minute: the HUD (top right), a PRIME BEARISH label and the TQS line in its own panel below. Shown for illustration only.

NEW TO SETUP SCORING

Read the chart at a glance

A score is only useful when you can see what drives it. StoryTeller shows the TQS, its four parts, a direction (the bias) and a one-line summary.

TQS line	Total Quality Score, 0–100, in its own panel: green 75+, cyan 55+, amber 40+, gray 25+, red below.
PRIME ▲ ▼	PRIME BULLISH arrow below the bar or PRIME BEARISH above, labeled with the TQS.
Verdict	CONTINUATION at TQS 70+, LEAN at 40–69, NO EDGE below 40; NO BIAS YET or NEUTRAL without a bias.
Bias	–1.00 (bearish) to +1.00 (bullish). [BULLISH] or [BEARISH] at Min Bias Strength (0.40), else [NEUTRAL].
PRIME blocked	Names the first gate that held a PRIME back.
Story	One-line summary; the dot is the bias. Not a signal.

Reading the HUD

Day / Open	Day type and confidence; how the open met the overnight range; overnight inventory.
Trend / Loc	Trend, opening drive, pullback grade; location and participation.
Exh / Level	Exhaustion (red from LATE up); nearest level within reach: Hold, Break or Fakeout.
Ctx Exe Flo Rsk	The four parts of TQS, 0–100. Higher Rsk = fewer red flags.

Hover any HUD row for a full explanation. Drag the HUD anywhere; the spot is saved and HUD Position becomes Custom.

FOR EXPERIENCED TRADERS

The rules, exactly

TQS	Ctx 25%, Exe 35%, Flo 30%, Rsk 10%, rescaled to add up to 1. With Drive and PB both under 50, Exe drops out and its weight is shared.
Bias	Trend ± 0.45 , TrendUp/TrendDown day ± 0.20 , overnight inventory, a sweep or absorption shift in the last 5 bars, and the nearest level. Halved at LATE or NEAR EXHAUSTION.
PRIME	On a closed bar: TQS ≥ 70 , bias ≥ 0.40 either way, exhaustion ≤ 65 , location ≥ 55 , and 20 bars since the last PRIME that way.
Session	New York time, whatever your time zone: RTH 9:30–16:00 ET, the day from the 18:00 ET Globex open, a 5-minute opening range.

Get started in three steps

1. Find your license key and the download at whop.com/steelysystems (SteelyIndicators Download). Both are also in your purchase email.
2. In NinjaTrader 8: Tools > Import > NinjaScript Add-On, then select SteelyIndicators.zip (keep it zipped).
3. Right-click a chart > Indicators > add **SteelyStoryTeller**, and paste your license key when asked. Defaults are ready to use.

Useful settings

Prime Threshold (70) · Min Bias Strength (0.4) · Weight: Context ... Red Flags · Require No Exhaustion · Require Good Location · Prime Bullish/Bearish Sound (live only) · Enable Flash (tints the verdict row) · Show Levels on Chart.