

What it does: SteelySuperHUD puts the read-outs of five SteelySystems indicators (trend and value, regression channel, momentum and flow, opening range, day type) in one draggable panel, with a live headline feed. It recalculates them itself and **draws nothing on the chart**.



The SteelySuperHUD panel: Trend / Value, Channel, Momentum / Flow, Opening Range, Story and News sections. Shown for illustration only.

NEW TO MARKET CONTEXT

Read the panel at a glance

Five sections read out the last closed bar, each ported from a SteelySystems indicator you don't need installed. A sixth carries live headlines. Any section can be hidden.

Trend / Value	TREND BULL or BEAR (EMA 9 vs 20), close ABOVE or BELOW session VWAP, EMA values, 20-bar POC.
Channel	Regression channel on closes, not drawn: direction, width, strength (R^2) and the close's position, 0–100%.
Momentum / Flow	ATR vs its average, RSI momentum, ADX strength, 10-bar up/down volume split, stochastic agreement.
Opening Range	OR high, low, mid and size; 09:30–09:45 ET by default, from 1-minute bars.
Story	Day type so far with confidence and stage, the nearest level's Hold, Break or Fakeout, a one-line summary.
News	FinancialJuice headlines, hot words in amber; Truth Social posts on top (Show Trump Posts).

Reading the panel

▲ ▼ ●	The summary's lean: bullish, bearish or none.
After →	A brief read, e.g. not aligned or bias unclear.
building	Not ready yet; at load the title counts down warm-up bars.
News status	Headlines held and time since the last good poll; amber when throttled or retrying.

Hover any row for a full explanation. Drag the panel anywhere (saved with the workspace); double-click its title to put it back.

FOR EXPERIENCED TRADERS

The rules, exactly

Closed bars	Calculate is fixed to On bar close: every row reads the last closed bar. No plots, drawings, alerts or account data.
Lean	EMA trend ± 0.20 ; VWAP side, channel (R^2 0.50+), RSI 60/40 and TrendUp/TrendDown day ± 0.15 each; volume split and OR break ± 0.10 each. Needs ± 0.35 .
Channel	Starts after Channel Period (20) bars, then grows; bands ± 2.0 SD. Restarts after 2 closes in a row outside (3-bar cooldown) and each trading day.
Day type	Rescored every 5 bars; a new type needs an 8-point lead (15 once CONFIRMED at 60 bars).
Levels	PDH, PDL, ORH, ORL, VWAP, POC, named within 4 × Level Proximity. Session values follow the chart's Trading Hours.

Get started in three steps

1. Find your license key and the download at whop.com/steelysystems (SteelyIndicators Download). Both are also in your purchase email.
2. In NinjaTrader 8: Tools > Import > NinjaScript Add-On, then select SteelyIndicators.zip (keep it zipped).
3. Right-click a chart > Indicators > add **SteelySuperHUD**, and paste your license key when asked. Defaults are ready to use.

Useful settings

Opening Range Anchor (New York RTH Open) · **Opening Range Start/End** (0/15 min) · **EMA Fast/Slow Period** · **Channel Period** · **Level Proximity** (ticks) · **Show ... Section** · **HUD Location** · **HUD Font Size** · **Show Trump Posts** (on).