

What it does: SteelyAlphaFlowX scores each closed bar against 30 confluence criteria (order flow, VWAP bands, volume profile, key levels, trend, breadth, gamma levels), labels a signal when one side reaches the threshold, shows **which criteria scored**, and keeps re-scoring it afterward.



MNQ, 5-minute: BULL / BEAR signal labels with stars, scores and tags, level lines, and the HUD (top left); bar delta and CVD in the lower panel. Shown for illustration only.

NEW TO CONFLUENCE SCORING

Read the chart at a glance

Confluence means independent conditions agreeing at once. SteelyAlphaFlowX scores each for the bullish or bearish side and labels a signal when one side's total reaches the threshold.

▲ BULL ★★ (7)	A confirmed signal and its score: ★ under 6, ★★ 6–7, ★★★ 8+. Overnight, scores under 6 show only ▲ (n).
[MR-2σ↑] / [KLR]	The VWAP band that scored (MR mean-reversion, MOM momentum), or a Key Level Reversal at an HTF zone.
[Δ EXHST?]	Score 8+ on a bar taller than ATR closing beyond the VWAP 2σ band: yellow label, no sound.
☒ INV / ☉ P1-P3	Invalidation 0.75 × ATR beyond the signal bar. Projections start at 1.5, 2.0, 4.5 × ATR (P3 6.1 on trend days); P2 needs ★★, P3 ★★★.
Health dots	Lime STRONG, yellow OK, orange DEGRADING, orange-red FAILING: the signal re-scored on each later bar.

Reading the HUD

State	POS GAMMA above the Gamma Flip, NEG GAMMA below; EMA ▲/▼ when no flip is set.
Closed / Checks	Last bar's ▲/▼ scores and Min, the score needed now. Checks: the criteria that scored.
Health	STRONG / OK / DEGRADING / FAILING for the last signal.
Past	Past signals, hypothetical, not a forecast: the share of recent signals (score 6+) that reached P1, P2 or invalidation.

Hover any HUD row for a full explanation. Drag the panel anywhere; Status shows READY or what needs attention.

FOR EXPERIENCED TRADERS

The rules, exactly

Closed bars	Signals score the just-closed bar on the next bar's first tick. Pending alerts and the live strip are previews.
Threshold	Profile: Conservative 7, Standard 6, Aggressive 5 (Prime 9, 8, 7); 2 lower outside 9:30–16:00 ET; volatility moves it –1 to +2. If both sides qualify, the higher wins.
Gates	Held back 3 bars and 8 minutes after a same-side signal, in news or macro blackouts, against your Session Bias, and while a monitored signal is STRONG/OK: other side below its score, same side below 7.
Gamma	Type the day's flip and walls in the Gamma settings; once the flip is set, the State row shows POS or NEG GAMMA [MANUAL]. Above the flip, band scoring is mean-reversion (MR); below, momentum (MOM). Against regime and EMA stack: threshold +2 (Standard).
Health	Re-scored each bar: STRONG at or above its score, OK at or above the threshold, DEGRADING up to 2 below, else FAILING. Clears, dots removed, after 20 bars or sooner.

Get started in three steps

- Find your license key and the download at whop.com/steelysystems (SteelyIndicators Download). Both are also in your purchase email.
- In NinjaTrader 8: Tools › Import › NinjaScript Add-On, then select SteelyIndicators.zip (keep it zipped).
- Right-click a chart › Indicators › add **SteelyAlphaFlowX**, paste your license key when asked, then type the day's gamma levels.

Useful settings

Profile (Standard) · Session Bias, News Time 1–3 (ET, HHMM) and Macro Event Today (today only; set each day) · Gamma Flip Level, Put Wall (Support Floor) and Call Wall (Resistance Ceiling) (typed daily) · Show Invalidation/Projection Lines · Show Advanced Settings.