

What it does: SteelyBreakRetest draws a level when price breaks out of a consolidation, then watches for price to return, test it and hold. Each retest that passes is labeled **A+**, **PRIME** or **STD**. Everything is decided at the **bar close**.



MNQ, 1-minute: PRIME bullish and bearish retest labels with their vote counts, and the HUD (top right). Shown for illustration only.

NEW TO BREAK AND RETEST

Read the chart at a glance

A break and retest has two parts: price closes through a level, then comes back to it and closes on the breakout side again. SteelyBreakRetest marks the level and labels each retest that passes.

Breakout line	Blue (bullish) or purple (bearish) at the broken level; removed when its setup fires or ends.
A+ BULL / BEAR	Gold: all 4 votes, plus the stack zone and a pin bar.
PRIME BULL / BEAR	Green (bullish) or red (bearish): 3 or 4 votes.
STD BULL / BEAR	Gray: 2 votes, the fewest any label needs.
[3/4 S P]	Votes out of 4; S = stack zone (level, VWAP and nearer EMA within $0.35 \times \text{ATR}$); P = pin bar.

Reading the HUD

TREND / EMA	BULL when the fast EMA (9) is above the slow (20), else BEAR; EMA shows both values.
VWAP / POC	Close ABOVE or BELOW VWAP; POC = most volume since the VWAP reset, *NEAR* within $0.5 \times \text{ATR}$.
STACK / VOL	STACK YES *A+* when a watched setup is in the stack zone; VOL = volume vs its recent average.
SETUP / PREV	BULL WATCH or BEAR WATCH with the level, or IDLE; PREV = the last label and its age.

Enable Signal Tracker adds PROJ, TIER and BASE rows: past signals, hypothetical, not a forecast. Hover any row for details.

FOR EXPERIENCED TRADERS

The rules, exactly

Breakout	A close beyond the high (low) of the Consolidation Bars by $0.35 \times \text{ATR}(14)$ or more, with a body of 45%+ that way and volume over $1.3 \times$ their average.
Retest	Within 12 bars: a wick to within $0.5 \times \text{ATR}$ of the level (at most $0.40 \times \text{ATR}$ past it), a close a tick or more back on the breakout side within $1.5 \times \text{ATR}$, and a confirming candle.
Votes	Bullish (bearish mirrors): fast EMA above slow, close above VWAP, close within $0.5 \times \text{ATR}$ of POC, retest volume under 85% of the breakout bar's. Needs 2+.
Watch ends	On a label, after 12 bars, a close back through the level past the retest tolerance, an opposite breakout, a $1.5 \times \text{ATR}$ run-away (6+ bars after the breakout), or a new session.
Presets	Values are Standard at 4-5 minutes. Conservative and Aggressive move nine at once; Auto Scale By Period adjusts other minute charts. Same-way labels: 5+ bars apart.

Get started in three steps

1. Find your license key and the download at whop.com/steelysystems (SteelyIndicators Download). Both are also in your purchase email.
2. In NinjaTrader 8: Tools > Import > NinjaScript Add-On, then select SteelyIndicators.zip (keep it zipped).
3. Right-click a chart > Indicators > add **SteelyBreakRetest**, and paste your license key when asked. Defaults are ready to use.

Useful settings

Signal Preset · Require A+ Only · Signals In RTH Only · Auto Scale By Period · VWAP Anchor Mode · Breakout Line Cleanup · Enable Signal Tracker (off) · NT8 Alert Popups. Right-click still opens the chart menu.