

What it does: SteelyEliteRibbon combines a five-EMA ribbon (8/13/21/48/200), colored by trend alignment, with ATR levels measured from the last completed higher-timeframe close (daily by default). 13/48 cross arrows, trend flips and breach markers are judged on the **closed bar**.



MNQ, 10-minute: ribbon clouds, Prev Close, Session Open and $\pm 23.6\%$ lines, the shaded no-edge zone and the info panel (top left). Shown for illustration only.

NEW TO EMA RIBBONS

Read the chart at a glance

EMAs 8, 21 and 48 set the trend: fast above slow is up, fast below slow is down. ATR levels show how far price is from the prior period's close.

Green / Blue	Fast cloud (EMA 8–21) green while $8 > 21$; slow cloud (21–48) blue while $21 > 48$. Both: full bull .
Red / Orange	The mirror; both red and orange: full bear . Mixed clouds turn EMA 8 light yellow.
Arrows ▲ / ▼	EMA 13 crossed above/below EMA 48 at bar close.
Prev Close	White line: the last completed ATR Mode close (daily by default), the levels' anchor.
ATR lines	Prev Close $\pm 23.6\%$ (yellow), 61.8% (blue), 100% (green) of the ATR; gray at 38.2, 50, 78.6%.
Zones · breach	Gray no-edge zone inside $\pm 23.6\%$; projection zones 61.8–100%. ▲/▼ text: a close beyond $\pm 100\%$.

Reading the info panel

Mode	SCALP 60-min, DAY, MULTIDAY weekly, SWING monthly, POSITION quarterly, LONGTERM yearly.
Trend	▲ BULL $8 > 21 > 48$, ▼ BEAR $8 < 21 < 48$ or ♦ MIX. Can change before the bar closes.
Range	This period's true range as % of ATR; 0% until a live tick.
Spread	EMA 8 – EMA 48 as % of price; near 0 = bunched.
ATR	ATR of the ATR Mode bars (ATR Length 14), in points.

Text color = trend. Hover a field for details; drag the panel to move it.

FOR EXPERIENCED TRADERS

The rules, exactly

Trend state	Full bull: $8 > 21 > 48$. Full bear: 8 not above 21 and 21 not above 48. Else MIX.
Closed bars	Arrows, trend-flip alerts and breach markers are judged once, on the closed bar, so live matches a reload. Clouds and Trend follow the forming bar.
ATR levels	Line = Prev Close $\pm \% \times \text{ATR}$ (14-period Wilder ATR of completed ATR Mode bars). Lines change only when a new one closes.
Session Open	Cyan dotted line: the open of the chart's session (Trading Hours template); on ETH, 6 PM ET, not 9:30.
Alerts	Off by default. Trend Flip, Conviction, Level Breach: at bar close. Level Touch: within 4 ticks of a main line. Re-arm 30 s.

Get started in three steps

1. Find your license key and the download at whop.com/steelysystems (SteelyIndicators Download). Both are also in your purchase email.
2. In NinjaTrader 8: Tools > Import > NinjaScript Add-On, then select SteelyIndicators.zip (keep it zipped).
3. Right-click a chart > Indicators > add **SteelyEliteRibbon**, and paste your license key when asked. Defaults are ready to use.

Useful settings

ATR Mode (Day) · **ATR Length** (14) · **Trigger %** (0.236) · **Show All Fibonacci Levels** · **Show Zone Fills** · **Bias Candles** (off) · **Enable Alerts** (off) · **Info Panel Position**. Right-click still opens the chart menu.