

What it does: SteelyStoDiver finds divergence between price and four stochastics. **PRIME** is a two-pivot sequence that starts with all four stretched; **MINOR** is a classic divergence of their average. By default each starts as a SETUP and fires when a later **bar close** confirms it.



MNQ, 2-minute: a MINOR SETUP and MINOR BEAR label, the divergence line, the trend EMA and the HUD (top left). Shown for illustration only.

NEW TO STOCHASTIC DIVERGENCE

Read the chart at a glance

Divergence is price and momentum disagreeing: a lower low in price with a higher low in the stochastic (bullish), or the mirror (bearish). SteelyStoDiver labels each one by the checks it passed.

PRIME	PRIME SETUP , then PRIME BULL (green) or PRIME BEAR (red) once a later bar confirms it.
MINOR	Cyan MINOR SETUP , then MINOR BULL / BEAR : divergence on the four-stochastic average.
RAW DIV	Blue: a blocked MINOR divergence; orange POST-CAUTION DIV within 15 bars of a PRIME CAUTION.
PRIME CAUTION	Gold diamond: the fast stochastic's K crosses its D against an active PRIME, ending it.
Lines	Join the price pivots: solid PRIME, dashed MINOR.

Reading the HUD

BIAS / QUAD	EMA trend with ATR and EMA period; QUAD counts stochastics oversold (OS) and overbought (OB).
STAGE	PRIME progress per side: L1 LOADED, L1+BOUNCE, SETUP ARMED or SCANNING.
SIGNAL / MINOR	Active signal, pending setups with AGE, and BLOCK: the filter holding a setup back.
TRIGGER / INVALID	The close that confirms the pending setup, and the price that cancels it.

STRENGTH METER (0-10, display only), MOMENTUM, ADX, FLOW and MTF add context; CAUTION WATCH counts bars since a PRIME CAUTION. Hover any row for details.

FOR EXPERIENCED TRADERS

The rules, exactly

Stochastics	K periods 9 (fast), 14, 40, 60. Oversold: K 20 or less; overbought: 80+. Pivots need 2 bars each side, so labels come 2 bars later.
PRIME	L1 : pivot low, all 4 oversold. Bounce : fast K back above 20. L2 : later pivot low at or below L1, higher fast K, fast K above 20. Bearish mirrors.
MINOR	Last two pivot lows: price lower, four-stochastic average higher. Blocked by Trend Gate, the ATR filter or a close beyond the pivot, it shows as RAW DIV.
Confirm	A SETUP fires within 6 bars (PRIME) or 4 (MINOR) on a close beyond the setup bar's high (low) as a green (red) candle. A bar through the pivot cancels it.
Filters	Block Strong Countertrend (on): no BULL in a BEARISH trend with RSI 40 or less and ADX 25+, and the mirror. Filters are rechecked at confirmation.

Get started in three steps

1. Find your license key and the download at whop.com/steelysystems (SteelyIndicators Download). Both are also in your purchase email.
2. In NinjaTrader 8: Tools > Import > NinjaScript Add-On, then select SteelyIndicators.zip (keep it zipped).
3. Right-click a chart > Indicators > add **SteelyStoDiver**, and paste your license key when asked. Defaults are ready to use.

Useful settings

Required Alignment · **Use Confirmed Trigger** · **Trend Gate** (All) · **Block Strong Countertrend** · **Use ATR Filter** (off) · **Oversold Level / Overbought Level** (20 / 80) · **Signal Display** (All). Right-click still opens the chart menu.